

## Instruction Manual:

### Step 1:


Right click on “my computer” on “desk top” or “start menu” and click on the “manage”.



### Step2:


After open up the “computer management” , click the “Device Manager”.

Find the option “Universal Serial Bus controllers” → “eHome Infrared Receiver (USBCIR)” on the right side and right click on it then click the option “update Driver software ”.




Step 3:

Choose the option “Browse my computer for driver software”.




Step 4:

Choose the option “Let me pick from a list of device drivers on my computer”



### Step5:

Choose the option at the bottom “ USB Composite Device” and click “ Next”



### Step6:

Pop up the message “ Windows has successfully updated your driver software” means the device will work normally in Windows 7 system.

